

MX190 (API for MX100/DARWIN R01.02) Instructions for Patch 1

Overview of Corrections

This patch corrects errors related to the DARWIN API only (no changes were made to the MX100 API).

Corrections to R01.01

Fixes a bug in which an error occurs in the return value of a calculation channel in the function for getting binary data (getChDataByBinary).

Corrections to R01.01 and R01.02

Corrects the situation in which an error occurs with the binary data declaration function (talkDataByBinary) depending on the channel range.

Installation

Expand the archive, then run the Setup.exe program located in the folder created.

Updated Modules

The Setup.exe program copies the following modules (initially installed by the API for MX100/DARWIN installer) to the target directory, automatically overwriting any existing modules having the same name.

API's for DARWIN

- DAQDARWIN.dll
 - DAQDARWIN.lib
-

Affected Revisions

This patch is applicable only to the following revisions.

MX190 (API for MX100/DARWIN)

- R01.01
 - R01.02
-

Confirming the Update

Confirm that update date and time of the updated modules is 2004/02/18 01:02.

Problems during Installation

If the patch fails to install, delete the API for MX100/DARWIN from your system, reinstall the API, then reinstall the patch. To delete the API, run Add/Remove Programs from the Control Panel.
